

Uemacs Editor Help Commands

Screen/Cursor Movement Commands

^A Move to start of line	ESC A Apropos (list some commands)
^B Move backward by characters	ESC B Backup by words
^C Insert space	ESC C Initial capitalise word
^D Forward delete	ESC D Delete forward word
^E Goto end of line	ESC E Reset Encryption Key
^F Move forward by characters	ESC F Advance by words
^G Abort out of things	ESC G Go to a line
^H Backward delete	
^I Insert tab/Set tab stops	
^J Insert , then indent	
^K Kill forward	ESC K Bind Key to function
^L Refresh the screen	ESC L Lower case word
^M Insert	ESC M Add global mode
^N Move forward by lines	ESC N Goto End paragraph
^O Open up a blank line	
^P Move backward by lines	ESC P Goto Beginning of paragraph
^Q Restart output	ESC Q Fill current paragraph
^R Search backwards	ESC R Search and replace
^S Stop output	
^T Transpose characters	
^U Repeat command four times	ESC U Upper case word
^V Move forward by pages	ESC V Move backward by pages
^W Kill region	ESC W Copy region to kill buffer
^Y Yank back from killbuffer	ESC X Execute named command
^Z Move backward by pages	ESC Z Save all buffers and exit

Window/ Buffer Commands

ESC ^A Change screen rows	
ESC ^C Count words in region	ESC ~ Unmark current buffer
ESC ^E Execute named procedure	
ESC ^F Goto matching fence	ESC ! Reposition endow
ESC ^H Delete backward word	ESC < Move to start of buffer
ESC ^K Unbind key from function	ESC > Move to end of buffer
ESC ^L Reposition window	ESC . Set mark
ESC ^M Delete global mode	ESC space Set mark
ESC ^N Rename current buffer	ESC rubout Delete backward word
ESC ^R Search & replace w/query	rubout Backward delete
ESC ^T Change screen columns	

ESC ^V Scroll next window down
ESC ^W Delete paragraph
ESC ^Z Scroll next window up

Exiting Uemacs and Other Key Commands

^X ? Describe a key	^X ! Run 1 command in a shell
^X = Show the cursor position	^X @ Pipe shell command to buffer
^X ^ Enlarge display window	^X # Filter buffer thru shell filter
^X O Delete current window	^X \$ Execute an external program
^X 1 Delete other windows	^X (Begin macro
^X 2 Split current window	^X) End macro
^X ^A Save current file	^X A Set variable value
^X ^B Display buffer list	^X B Switch a window to a buffer
^X ^C Exit MicroEMACS	^X C Start a new command processor
^X ^D Detab line	^X D Suspend MicroEMACS (BSD4.2 only)
^X ^E Entab line	^X E Execute macro
^X ^F Find file	^X F Set fill column
^X G Search forward	
^X ^I Insert file	
^X K Delete buffer	
^X ^L Lower case region	
^X ^M Delete Mode	^X M Add a mode
^X ^N Move window down	^X N Rename current filename
^X ^O Delete blank lines	^X O Move to the next window
^X ^P Move window up	^X P Move to the previous window
^X Q Insert literal	
^X ^R Get a file from disk	^X R Incremental reverse search
^X S Incremental forward search (Incremental search not always available)	
^X ^T Trim line	^X ^U Upper case region
^X ^V View file	
^X ^W Write a file to disk	^X W resize window
^X ^X Swap "." and mark	^X X Use next buffer
^X ^Z Shrink window	^X Z Enlarge display window

Usable Modes

WRAP	lines going past right margin "wrap" to a new line
VIEW	Read Only mode where no modifications are allowed
CMODE	Change behaviour of some commands to work better with C
EXACT	Exact case matching on search strings
OVER	Overwrite typed characters instead of inserting them
CRYPT	Current buffer will be encrypted on write, decrypted on read
MAGIC	Use regular expression matching in search
ASAVE	Save the file every 256 inserted characters